




## How to setup Zebra roll printer on Mac/Safari

### Before the installation make sure that:


- Your Flea Lover site is accessed via Safari and you have at least 1 customer created.
- The roll printer model is a Zebra.
- The roll printer is connected to the Mac via. USB.
- The roll printer is turned on, and a roll of labels are inserted correctly – test this by pressing the “feed” button on top of the printer: a single blank label is produced by the printer.

### Printer Installation:

1. Press cmd(⌘) + Spacebar and search “System Settings”.  
From there, scroll down to “Printers & Scanners” and click “Add Printer, Scanner or Fax...”




2. Select the Zebra roll printer from the list of available printers and click “Choose a driver” -> “Select Software...”







3. Choose the software according to your printer model and click “OK”.



4. Click “Add” to add the printer.




5. Your Zebra roll printer should now appear in the list of available printers.






### Configuring Safari for print:

1. Open your Safari browser and a
2. Access your Flea Lover system.
3. On the top of your screen: Click “Safari” and choose “Settings...”.



4. Under “Pop-up Windows” choose the option to allow pop-ups from app.flealover.com (otherwise Safari will block the print dialog from the system).



Close the window after.



## Configuring Flea Lover for print:

1. Access your Flea Lover System from Safari.
2. Choose a random customer and create a product sheet with a test product and mark the sheet as “finished”. Then click the button “Print Barcodes”.

Name	Details	Status	Created	Actions
Test	#1-40 (40 pcs)	Active	17-11-2025 11:59	

3. From the print pop-up: Click “OK” to print a label.

Print barcodes for customer ×

Shelf number


Print type

Labels to print

4. A page will show a preview of the chosen labels, from here click cmd(⌘) + P to initiate the print.



5. From the print dialog:  
Choose “Paper Size” and click “Manage Custom Sizes...”





- From there, click the “+” and set the Width and Height to you label size.  
Recommended: Set margin to 0 mm (if print is too close to the edge of the paper set margin to 1-2 mm).  
Double click the name of the preset, and name it “Flea Lover”.  
Click OK to save.

Flea Lover

Width: 38,1 mm

Height: 25,4 mm

Margins: User Defined

Top: 0 mm

Bottom: 0 mm

Left: 0 mm

Right: 0 mm

Cancel OK

- Save the settings by clicking on “Presets” and choose “Save Current Settings as Preset...”.

Printer: Zebra Technologies ZTC GK420d (Seren's MacBook Pro)

Presets: Default Settings, Last Used Settings, **Save Current Settings as Preset...**

Copies: 1

Pages: All Pages

Paper Size: Flea Lover 38 by 25 mm

Orientation: Portrait

Scaling: 100 %

Cancel Print

- Rename your new preset “Flea Lover”:

Preset Name: Flea Lover

Available For:  Zebra Technologies ZTC GK420d  
 All printers

Type:  Custom Preset  
 Print Job Preset

Cancel OK

Click “OK”. This saves the paper settings for future prints.



9. Hit the “Print” button and your first label should be produced by the roll printer.

A screenshot of a printer settings dialog box. On the left is a preview of a label with the following text: "DKK 2000.00 100", "Product Test", a barcode, "Page 1 of 1", and "kbrq.....430". The right side of the dialog contains the following settings: "Printer" set to "Zebra Technologies ZTC GK420d (Saren's MacBook Pro)", "Presets" set to "Custom", "Copies" set to "1", "Pages" with "All Pages" selected, "Paper Size" set to "Flea Lover 38 by 25 mm", "Orientation" set to "Portrait", and "Scaling" set to "100 %". At the bottom right, there are "Cancel" and "Print" buttons, with the "Print" button highlighted by a green rectangular box.